

definitions

image

a static snapshot of container's configuration.

= container

an application sandbox. each container is based on an image.

layer

image is composed of read-only file system layers. container creates single writable layer.



docker registry

remote server for storing Docker images



Dockerfile

a configuration file wih build instructions for Docker images



docker engine installation running

Docker platform on a given host



docker client

client application that talks to local or remote Docker daemon



docker daemon

service process that listens to

Docker client commands over local or remote network



docker host

server that runs Docker engine



volume

directory shared between host and container

docker run

docker run [OPTIONS] IMAGE[:TAG] [COMMAND]

Run a command in a new container.

metadata

--name=CNTNR NAME Assign a name to the container.

-1, --label NAME[=VALUE]

Set metadata on the container.

-d. --detach Run in the background. Keep STDIN open. -i, --interactive

Allocate a pseudo-TTY. -t, --ttv

Automatically remove the container

when process exits.

-u USER Run as username or UID. Give extended privileges. --privileged

Set working directory. -w DIR

-e NAME=VALUE Set environment variable.

--restart=POLICY Restart policy.

> no on-failure[:RETRIES] unless-stopped

-P, --publish-all Publish all exposed ports to random

-p HOST PORT: CNTNR PORT

Expose a port or a range of ports.

network --network=NETWORK NAME

Connect container to a network.

--dns=DNS_SERVER1[,DNS_SERVER2]

Set custom dns servers

--add-host=HOSTNAME: IP

Add a line to /etc/hosts.

Mount the container's root file --read-only system as read only.

-v, --volume [HOST SRC:]CNTNR DEST

Mount a volume between host and the container file system.

--volumes-from=CNTNR ID

file system

Mount all volumes from another container.

Dockerfile

FROM <image id>

RUN <command>

base image to build this image from

RUN ["<executable>",

"<param1>",

exec form

"<paramN>"1

executes command to modify container's file system state

shell form

MAINTAINER < name>

provides information about image creator

LABEL <key>=<value>

adds searchable metadata to image

ARG <name>[=<default value>]

defines overridable build-time parameter:

docker build --build-arg <name>=<value> .

ENV <key>=<value>

defines environment variable that will be visible during image build-time and container run-time

ADD <src> <dest>

copies files from <src> (file, directory or URL) and adds them to container file system under <dst> path

COPY <src> <dest> similar to ADD, does not support URLs

VOLUME <dest>

defines **mount point** to be shared with host or other containters

EXPOSE <port>

informs Docker engine that container listens to **port** at run-time

WORKDIR <dest>

sets build-time and run-time working directory

USER

defines run-time user to start container process

STOPSIGNAL <signal>

defines signal to use to notify container process to stop

ENTRYPOINT

shell form or exec form

defines run-time **command prefix** that will be added to all run commands executed by docker run

CMD

shell form or exec form

defines run-time command to be executed by default when docker run command is executed

